

INTEGRITI INTEGRATION – Hanwha Wisenet Wave CCTV RELEASE NOTES V1.6

INNERRANGE.COM

inner range
INTEGRITI

CONTENTS

CONTENTS 2
OVERVIEW 3
THIS RELEASE 3
Release Requirements 3
Built with 3
Compatibility with vendor systems 3
Tested against 3
Release includes 4
Installation and Configuration 4
CCTV CAPABILITIES 5
PAST RELEASE INFORMATION 9
Version 1.5 9
Version 1.4 9
Version 1.3 10
Version 1.2 10
Version 1.1 10
Version 1.0 11

OVERVIEW

The Hanwha Wisenet Wave Integration is a third-party CCTV integration with the Integriti platform, enabling key functionality from Hanwha Wave CCTV systems to be monitored and controlled directly within the Integriti software suite. This integration consolidates access control, intruder detection, and CCTV management into a single, unified interface. Users can view live and recorded footage, retrieve event data, and control PTZ presets and other camera features, all from within Integriti. For a detailed list of supported features, please refer to the CCTV Capabilities.

Term: For brevity, ***Hanwha Wisenet Wave*** is referred to as ***Hanwha Wave*** in this document.

THIS RELEASE

Version 1.6

Released May 2025

Release Requirements

Required Integriti Version License	Integriti Pro/Infiniti v25 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v24 or higher
Integriti Licensing Requirements	For Integriti Business, one CCTV License is required per camera to be used in the system. Integriti Business supports 32 Cameras initially, and additional cameras can be added in lots of 8 using the 996921 CCTV - Extra 8 Cameras license. Any unlicensed Cameras will still show up in Integriti; however, they will not be useable. For Integriti Corporate, unlimited cameras are supported with no additional licenses required.

Built with

NX Witness SDK v6.0

Note: NX, Hanwha and DW Spectrum products all use NX Witness SDK as core technology component. Accordingly, our integration plugins for NX, Hanwha and DW Spectrum CCTV systems use this SDK for communicating to their respective vendor systems.

Compatibility with vendor systems

The plugin works with Hanwha Wave CCTV v5.1 and v6

The Integration will only work with Hanwha Wisenet Wave systems. Use the Integriti Hanwha Techwin CCTV Integration for connecting to Hanwha Techwin and Hanwha Wisenet NVRs.

Tested against

The plugin was tested against the following versions of software:

- Hanwha Wave CCTV server v5.1.2 (limited testing)
- Hanwha Wave CCTV server v6.0.1

Release includes

New Features

- Support of NX Witness API v6

Feature Updates

- Support of LPR notifications generated by:
  - Hanwha cameras running RoadWatch and RoadAI applications
  - AXIS cameras running CammraAI and License Plate Verifier applications
  - HikVision LPR
  - MileSight cameras

Installation and Configuration

The plugin installer replaces an installed version with the new one.

For specific configuration instructions refer to the plugin's Manual document. The Manual also includes information about LPR functionality.

CCTV CAPABILITIES

Core CCTV Capabilities

Feature	Feature Description	Y/N
Stream Live CCTV Footage	Live CCTV footage can be streamed from online cameras in the CCTV system to an Integriti client.	✓
Select Custom Aspect Ratio	Select the aspect ratio to use when streaming CCTV footage on a per-camera or per-recorder basis.	✓
Stream Archived CCTV Footage	Archived CCTV footage can be streamed from online cameras in the CCTV system to an Integriti client.	✓
Control Archived CCTV Playback Speed	Playback speed of archived CCTV footage can be controlled from the Integriti client.	✓
Auto-Play CCTV Footage from Events	Live or archived CCTV footage can be configured to be automatically displayed when an event occurs in the Integriti System on a specific client workstation.	✓
Create Child Devices from Camera Configuration	Child CCTV Cameras will be created based on the Camera configuration on Refreshing Child Devices	✓
Associate Cameras With Entities	Cameras loaded from the CCTV system can be associated with Integriti Entities to allow direct control of one from the other.	✓
Show Associated CCTV From Event	Associated CCTV Footage can be directly accessed and viewed from any event occurring in Integriti that has an associated Camera (either a direct association or through the Entity that triggered the event)	✓
Control PTZ Cameras	Send PTZ commands to support cameras on the CCTV system to control the Pan, Tilt and Zoom of the camera directly from the video stream.	✓
Send Cameras to PTZ Preset	Send supported PTZ cameras on the CCTV system to preconfigured PTZ presets directly from the video stream.	✓
Digital PTZ Control	Digitally zoom the CCTV stream's image for non-PTZ cameras and archived footage.	✓
CCTV Layouts	Store a collection of Cameras with an specific viewer layout to be brought up at a later point in time	✓

Feature	Feature Description	Y/N
CCTV Surrounding Cameras View	Show a selected camera, as well as the cameras configured to be N, NE, E, SE, S, SW, W and NW of the selected camera, quickly jumping between surrounding streams directly from the view.	✓
Trigger Actions in the CCTV System	Trigger actions or commands in the CCTV system directly from Integriti.	✓
View and Control Cameras on Schematics	Cameras can be added to Schematics Maps in Integriti and directly viewed and controlled directly from the Schematic. Each camera's state is immediately visible on the Schematic where available.	✓
Sync Time (via NTP)	Sync the time of the CCTV system and Integriti to match via an NTP.	✓
Display Connection Status to CCTV System	Display whether or not Integriti is currently connected to the CCTV system.	✓
Receive Events/Alarms from the CCTV System	Log events/alarms occurring on the CCTV system to Integriti's Review.	✓
Trigger Integriti Actions on CCTV Events/Alarms	Trigger actions to automatically occur in Integriti whenever specific events/alarms are received from the CCTV system.	✓
Generate Alerts from CCTV Events/Alarms	Automatically generate and restore Alerts tied to a specific Camera in Integriti whenever specific events/alarms are received from the CCTV system.	✓

Advanced CCTV Capabilities

Feature	Feature Description	Y/N
Automatically Load Camera Configuration	Refreshing Child Devices will automatically populate all cameras configured in the CCTV System into Integriti when run. If not supported, camera configuration will need to be manually entered into Integriti.	✓
64-bit Integration Server Support	The integration supports being run on the 64-bit integration server.	✓
Show Camera Status	The current online/offline status of configured cameras will be visible directly through Integriti.	✓

Feature	Feature Description	Y/N
Categorised Review Records	Review generated by the integration will have a different category for different event types, allowing for easy filtering of specific CCTV events	✓
License Plate Recognition	License plates recognised by supported cameras in the CCTV system can be used to automatically allow access to configured Doors.	✓
Trigger Inputs on CCTV Event	Inputs in Integriti can be automatically triggered and restored when specified types of events are received from the CCTV system.	✓
Control Iris and Focus	Control the iris and focus of supported cameras on the CCTV system directly from the video stream	✗
Control PTZ Tours	PTZ Tours can be started and stopped directly from the video stream.	✓
Display Video Frame Times	When viewing archived CCTV footage, the time of the current frame will be displayed on the viewer control.	✗
Show On-Screen Display	Enable additional information (such as camera name and current playback time) to be displayed as an overlay on video streams.	✗
Reverse Playback	When viewing archived CCTV footage, the footage can be played in reverse.	✗
Step Forward/Backward	When viewing archived CCTV footage, the footage can be stepped through one frame at a time.	✗
Export CCTV Clips	Export video clip of archived CCTV footage to the Evidence Vault or to a file directly from Integriti.	✓
Export CCTV Snapshots	Export still snapshot of archived CCTV footage to the Evidence Vault or to a file directly from Integriti.	✗
Export Current Frame	Export still snapshot of the current frame in the CCTV Viewer to the Evidence Vault or to a file directly from the CCTV Viewer.	✗
Stream Audio With Video	Receive audio from the microphone on a supported CCTV camera through an Integriti client workstation	✗

Feature	Feature Description	Y/N
Send Audio to CCTV Camera	Send audio from an Integriti client workstation out of the speakers on a supported CCTV camera.	✘

PAST RELEASE INFORMATION

Version 1.5

Released April 2024

Required Integriti Version License	Integriti Pro/Infiniti v23 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v22 or higher

BUILT WITH
NX Witness SDK v4

TESTED AGAINST
- Wisenet WAVE Server v4.0.0.29988 x64
- Wisenet WAVE Server v5.0.0.35270 x64

RELEASE INCLUDES
New Features
- Added support for Integriti to receive LPR events from the Wisenet WAVE Server. LPR events contain the time of the event, license plate number and the source camera that captured the license plate.

Version 1.4

Released November 2022

Required Integriti Version License	Integriti Pro/Infiniti v22 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v21 or higher

BUILT WITH
NX Witness SDK v4

TESTED AGAINST
- Wisenet WAVE Server v4.0.0.29988 x64
- Wisenet WAVE Server v5.0.0.35270 x64

RELEASE INCLUDES
Issues Resolved
- **Export**: Removed the ability to access the unsupported export snapshot command which resulted in unnecessary error messages.

- **Persisted Connection**: Resolved an issue that signalled persisted connection online when the connection failed to start.

Version 1.3

Released November 2020

Required Integriti Version License	Integriti Pro/Infiniti v20 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v20 or higher

BUILT WITH
NX Witness SDK v4

TESTED AGAINST
- Wisenet WAVE Server v4.0.0.29988 x64

RELEASE INCLUDES
Issues Resolved
- **Event Monitoring:** Resolved potential issue that could result in errors occurring when processing unsupported event types.

Version 1.2

Released October 2020

Required Integriti Version License	Integriti Pro/Infiniti v20 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v20 or higher

BUILT WITH
NX Witness SDK v4

TESTED AGAINST
- Wisenet WAVE Server v4.0.0.29988 x64

RELEASE INCLUDES
Issues Resolved
- **Refresh Child Devices:** Resolved issue resulting in an error occurring when Refreshing Child Devices on some systems.

Version 1.1

Released September 2020

Required Integriti Version License	Integriti Pro/Infiniti v20 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v20 or higher

BUILT WITH
NX Witness SDK v4

TESTED AGAINST
- Wisenet WAVE Server v4.0.0.29988 x64

RELEASE INCLUDES
New Features
- **Connection**: Added the HTTPS secure connection option

Issues Resolved
- **Video Viewer:** Resolved an issue that prevented viewing video when recorder credentials contained special characters.
- **Refresh Child Devices:** Resolved an issue that prevented the plugin to retrieve child devices when connected directly to an NVR.

Version 1.0

Released June 2020

Required Integriti Version License	Integriti Pro/Infiniti v20 license
Minimum Installed Integriti Version	Integriti Pro/Infiniti v20 or higher

BUILT WITH
NX Witness SDK v4

TESTED AGAINST
- Wisenet WAVE Server v4.0.0.29988 x64

RELEASE INCLUDES
Initial release



Global Headquarters

Inner Range Australia
+61 3 9780 4300
sales.au@innerrange.com

Inner Range United States
+1 (844) 588-0874
sales.usa@innerrange.com

Inner Range United Kingdom
+44 (0) 845 470 5000
sales.uk@innerrange.com

Inner Range Canada
+1 (844) 588-0874
sales.canada@innerrange.com

Inner Range Middle East
+971 4 8067100
sales.me@innerrange.com

Inner Range India
+91 80 4070 3333
sales.india@innerrange.com

INNERRANGE.COM